NAS Manager User's manual

SyncQuick[™] NAS Manager is a NAS device searching and backup software that has been specifically developed for NAS Client users to provide simple, fast and reliable backup for all personal information including photos, MP3-files, and other important documents.

1. NAS Search and entering NAS GUI

1. Run the Utility CD enclosed in package, and installed SyncQuick[™] NAS manager in to your computer.



2. Select Auto Search and when Turbo NAS is found, right click the mouse button and select **"Open NAS Control page"** to start configurations.

SEARCH	SAMBA	HELP		NASS Network Attached Storage
- Option Auto Sear 1 1		arch	End IP 192.168.1.255	2
Device Name	I	P Address	Mac Address	
STORAGE-1568	1	92.168.1.52	6A-B3-F6-00-15-68	
	Connect to NAS			
r i i i i i i i i i i i i i i i i i i i	Connect as different user			
	Open NAS Control Page	 3		

3. Default login is **"admin"** for both user name and password, click "**OK**" to enter configurations.



4. Enter to NAS GUI

			NAS
an 🔸 💻 📰 🖬	1 12 -		Network Attached Storage
Status		Identification	
Identification	Host name	STORAGE-0000	
Time Setting	Group name	WORKGROUP	
LAN Config	Administrator	admin	
Disk Utility			
Maintenance		Date and Time	
Samba Server	Date	2009/10/09 14:18:16 GMT 8:00	
WebDAV Server			
Media Server	Firmware Version	Disk Usage & Firmware G5S5020314152C0 L-1 20B	
Print Server	Free Size	76449 MB free	
BitTorrent			
Dictorient	Total Size	78533 MB	

2. Entering NAS folder

- Log in to NAS Folder, click right side of mouse button, and select "Connect to NAS".
- 2. Input NAS folder password.
- 3. Click "OK" to enter the NAS Folder.

			_		
SEARCH	SAMBA	HELP		LANGUAGE	
~ Option Auto Search	 Manual Search Start IP 19 	2.168.1.0	End IP	192.168.1.72	•
Device Name	IP Ac	Idress		Mac Address	
STORAGE Connect to N	192.1	68.1.72		00-B3-F6-00-00-00	
Connect as di Open NAS C		1	2		
		Login Details User Name Password	guest	OK Cancel	
			L	3	

4. A Public folder will be created by NAS by default, click in to the Public folder and user can now copy data between PC and NAS.

SyncQuick NAS M	anager					
_						
SEARCH	S	AMBA	HELP	LANGUA	GE	
Schedule Backup						
My Computer				STORAGE-0000		
過 我的文件			🜱 🖄 📑 🎞 🕶	🖄 📴 🎟 🗸		
Name	Туре	Size D	ate Modified 🛛 🔥	Name	Path	
🚞 Email				DUBLIC	\\STOR	AGE-0000\PUBLIC
💼 01-1.jpg	JPEG	36 KB 20	009/8/13.	(4) Click in to Pu	ublic folder	
				7 🖻 01-1.jpg		
				-		
	Drag a	and drop cop	у			
	Use	er's PC		NA	S Folder	
			>			
Source				Destination		

5. If you wish to create more folder please go to **NAS Control page**/ SMB/Add folder,Please refer to the NAS user's manual for the setup detail.

3. Log in to another user /folder

- Got to Search page again and right click Log in to NAS Folder, click right side of mouse button, and select "Connect as different user".
- 2. Enter the user name and Password. (for example: test is the folder you have created form NAS control page)
- 3. Click "**OK**" to log in the test folder.

SyncQuick NAS Manager					
		_	_		
SEARCH	SAMBA	HELP		LANGUAGE	
~ Option					
Auto Search	Manual Search				
	Start IP 192.1	68.1.0	End IP	192.168.1.72	b
					-
Device Name	IP Addre	ss		Mac Address	
STORAGE Connect to NA	\$ 192.168.	1.72		00-B3-F6-00-00-00	
Connect as dif	ferent user				
Open NAS Co	ntrol Page		\mathcal{O}		
			Ŷ		
	L	ogin Details			×
					7
		User Name	Test		
		Password	Test		
				OK Cancel	
					-
				1	
				(3)	

4. Scheduling Backup data in to NAS

- 1. The SAMBA section, click "**Schedule backup**" a back up setting page will pop up on the screen.
- 2. Select the a data source (Data you want to backup from) and a data destination, (For example: Back up my Tax file from PC to NAS test folder)
- 3. Select a copy frequency.
- 4. Enter the NAS folder user name and password. And click "**Save**" to create a back up list. You can create more than one backup job table here.
- 5. Select the backup job you just created and click"Start" to precede it.

	R BackupSettings						
SEARCH	Advance Backup Settings Hot Syn	ic Settings					
edule Backup	and the second second			Ý			
mputer	Backup Info						
L	Backup Source C:\Do	Backup Source C:\Documents and Settings\Tim\My Documents\etax					
り	Backup To	RAGE-029d\test					
	Select Frequency			r Source Folder security Settings-			
	MP1 Select Frequency MP1 Daily			User Name			
akeDVDVideo							
	O Weekdays			Password			
	O Monthly		~				
	After Each Select Day		~				
	On Selected Day	2009/10/12	~	Destination Folder security Settings-			
		0.2		User Name			
	Time To Backup		\$	test			
		14:42	Ŧ	Password ****			
	Backup List		(4 Save Cancel			
e			Next Run Tin	ne			
WC	C:\Documents and Se \	\\STORAGE-029d\test	2009/10 14:	42			
				(5)			
				Ų.			
	Edit		elete	Start			